How do I build MeshKit for EBMesh?

0. Prerequisites: If you'd like to read solid model based geometry files (iges, step, brep, sat, sab... etc.) <u>MeshKit</u> requires iGeom implementation, so you'll need to build/install it first. See <u>CgmFromScratch</u> for instructions. For iGeom build, you can choose a geometry engine such as OpenCASCADE and ACIS. OpenCASCADE is an opensource which can be downloaded from http://www.opencascade.org/getocc/download/loadocc/.

If you just read facet based geometry files (hdf5, genesis, stl ... etc.), you don't need to build iGeom implementation above.

In addition, <u>MeshKit</u> EBMesh requires iMesh implementation for its mesh data structure, so you need to build/install it too. See <u>MoabFromScratch</u>.

- 1. Grab the code straight from the repository using <u>Subversion</u>, by running 'svn co <u>https://svn.mcs.anl.gov/repos/fathom/MeshKit/trunk MeshKit</u>'.
- 2. Run 'autoreconf -fi' in the main source directory. NOTE: <u>MeshKit</u> relies on the autotools (autoconf, libtool, automake) that come with most LINUX/UNIX distributions. If they're not part of your OS, or you're getting mysterious autotools errors, you might want to try downloading/building more recent versions of those packages then trying again. On windows, try running cmake (though this is only indirectly supported, meaning it may not be up to date).
- 3. In the top-level source directory, run the configure script, with the various options you want. To get a list of options, run ./configure --help. To use EBMesh, you will need "./configure --with-imesh=(iMesh build directory path) --with-igeom=(iGeom build directory path)". You can remove "--with-igeom", if you only use facet based geometry.
- 4. Go to sub directory "algs/test" from the <u>MeshKit</u> top-level source directory. Run "make EBMesh_test" to make a EBMesh tool test executable. You can execute "EBMesh_test" with several options.

If you have problems running 'autoreconf -fi' or suspect that the build system is broken do to improperly installed versions of the GNU autotools then see: AutoToolsIssues.

When using --with-cgm option and CGM is build using --with-cubit option you might encounter segmentation fault and *** glibc detected *** errors. See <u>this</u> link for details.